

## Code Documentation: read\_Data.py

### 1. Reading PNG Image Files

The `read\_dataset` function processes PNG files and prepares image data and corresponding labels.

#### Code:

```
def read_dataset(lispath, target, resize_shape=(256, 256)):
    imgs = []
    for file in os.listdir(lispath):
        if file[-3:] == 'png':
            img = cv2.imread(os.path.join(lispath, file))
            img = cv2.cvtColor(img, cv2.COLOR_BGR2RGB)
            img = cv2.resize(img, resize_shape)
            imgs.append(np.array(img))
    labels = len(imgs) * [target]
    return np.array(imgs), np.array(labels)
```

#### Explanation:

##### - Inputs:

- `lispath`: Directory containing PNG files.
- `target`: Label to assign to all images.
- `resize\_shape`: Tuple defining the image resizing dimensions (default is `(256, 256)`).

##### - Process:

- Loops through all files in the specified directory.
- Checks for files ending with `.png`.
- Reads the image, converts its color from BGR to RGB, and resizes it.

##### - Outputs:

- `imgs`: Numpy array of image data.
- `labels`: Numpy array containing the specified `target` label repeated for all images.

### 2. Reading FITS Files

The `read\_fits` function extracts data from FITS files, commonly used in astronomy.

#### Code:

```
def read_fits(filename):
    try:
        with fits.open(filename) as hdul:
            data_matrix = hdul[0].data
            if len(hdul) > 1 and isinstance(hdul[1], fits.BinTableHDU):
```

```

        binary_table = hdul[1].data
        freqs = binary_table['FREQUENCY'][0]
        time = binary_table['TIME'][0]
    else:
        raise ValueError("Binary table not found or invalid structure.")
    if data_matrix.shape[0] != len(freqs) or data_matrix.shape[1] != len(time):
        raise ValueError("Data matrix dimensions do not match frequency and time axes.")
    return data_matrix, freqs, time
except Exception as e:
    print(f"Warning: Error reading FITS file '{filename}': {e}")
    return None, None, None

```

## Explanation:

### - Inputs:

- `filename`: Path to a FITS file.

### - Process:

- Opens the FITS file and extracts:
  - `data\_matrix`: 2D data matrix.
  - `freqs`: Frequency axis.
  - `time`: Time axis.
- Ensures the matrix dimensions align with the axes.

### - Outputs:

- `data\_matrix`: 2D array of data values.
- `freqs`: Array of frequency values.
- `time`: Array of time values.

## 3. Plotting FITS Data

The `plot\_fits\_data` function visualizes FITS data before and after background filtering.

### Code:

```

def plot_fits_data(data_matrix, freqs, time, title_raw='Raw Spectrum', title_filtered='Filtered
Spectrum', vmin=None, vmax=None):
    plt.figure(figsize=(12, 6))
    plt.subplot(1, 2, 1)
    plt.imshow(data_matrix, aspect='auto', extent=[time[0], time[-1], freqs[0], freqs[-1]],
origin='lower')
    plt.xlabel('Time (s)')
    plt.ylabel('Frequency (MHz)')
    plt.colorbar()
    plt.title(title_raw)

    background = np.mean(data_matrix, axis=1)
    background = np.tile(background, (data_matrix.shape[1], 1)).T

```

```

filtered_data = data_matrix - background
filtered_data = np.clip(filtered_data, -1, 25)

plt.subplot(1, 2, 2)
plt.imshow(filtered_data, aspect='auto', extent=[time[0], time[-1], freqs[0], freqs[-1]],
origin='lower')
plt.xlabel('Time (s)')
plt.ylabel('Frequency (MHz)')
plt.colorbar()
plt.title(title_filtered)

plt.tight_layout()
plt.show()

```

## Explanation:

### - Inputs:

- `data\_matrix`: Raw 2D data to visualize.
- `freqs` and `time`: Frequency and time axes.

### - Process:

- Displays two plots:
  1. **Raw Data**: Original data matrix.
  2. **Filtered Data**: Background-subtracted data, clipped to a specific range.

### - Features:

- Customizable titles (`title\_raw` and `title\_filtered`).
- Clipping of filtered data improves visualization.

## 4. Processing FITS Files in a Directory

The `read\_fits\_dataset` function processes all `.gz` compressed FITS files in a directory.

## Code:

```

def read_fits_dataset(path):
    images = []
    times = []
    freqs = []
    first_image_shape = None

    for file in tqdm(os.listdir(path)):
        try:
            if file.endswith(".gz"):
                img, freq, time = read_fits(os.path.join(path, file))

                if img is not None:
                    if first_image_shape is None:

```

```

        first_image_shape = img.shape

        img_resized = cv2.resize(img, (first_image_shape[1], first_image_shape[0]))
        images.append(img_resized)
        freqs.append(freq)
        times.append(time)
    except Exception as e:
        print(f"Warning: Error reading FITS file '{file}': {e}")

    return images, pd.DataFrame({'freqs': freqs, 'times': times})

```

## Explanation:

### - Inputs:

- `path`: Directory containing `.gz` compressed FITS files.

### - Process:

- Reads and processes each FITS file:
- Resizes images to match the first image's shape.
- Extracts frequency and time data.

### - Outputs:

- `images`: List of processed FITS image data.
- `data`: Pandas DataFrame containing the frequency and time data.